

FEITIAN EPASS NFC

The specifications and information in this document are subject to change without notice. Companies, names, and data used in examples herein are fictitious unless otherwise noted. This document may not be copied or distributed by any means, in whole or in part, for any reason, without the express written permission of RCDevs Security. WebADM and OpenOTP are trademarks of RCDevs. All further trademarks are the property of their respective owners.

No guarantee is given for the correctness of the information contained in this document. Please send any comments or corrections to info@rcdevs.com.

Limited Warranty - Copyright (c) 2010-2024 RCDevs Security SA. All Rights Reserved.

SSH Authentication with a Feitian ePass NFC/FIDO/U2F Security Key

Feitian ePass NFC FIDO U2F Security Key can work as a Generic Identity Device Specification (GIDS) smart card. There are also many other manufacturers and card models to which these instructions can be applied, but the specific tools to initialize the card can be different.

In this how-to, we will prepare a USB/NFC hardware key for SSH authentication and register the device in WebADM. It is assumed you already have a working WebADM and Spankey servers, although you can also deploy the public key manually to a destination server.

For Yubikeys and other PIV devices, please refer to Smart Card PIV

1. Enabling CCID Mode

Feitian ePass keys can work in three different modes:

- > FIDO
- > OATH HOTP (Event-based)
- > CCID (chip card interface device)

All these modes can be used with OpenOTP, but in this guide, we focus on the CCID which is useful for SSH authentication.

By default, the Feitian keys ship only have U2F/FIDO mode enabled, thus the first step is to change the operating mode of the key. This is done with a Feitian tool (ePassFIDO-NFC OTP Tool 3.7), which can be downloaded from Feitian website and which works in Windows.

Connect the key to a computer with the Feitian tool, start the tool and select an operating mode which includes CCID. The key can work simultaneously on all three modes. If the new mode includes U2F, you can continue to use the key for FIDO authentication simultaneously with SSH key authentication.

CLOWIC .				- U A
TEASE HID OBJ/CE U2E 0 is insected	Serial Number			
SAFE FILD DEVICE OZF O IS INATING	Key -			
	HOTP length 6 * Same	Random data		
	List user Info Reset applet. Version Info			
	Serial Number	Hotp code from card	Operator	
rtified				
All Devices				
Al Devices Al Devices E HID DEVICE U2F 0				
Al Devices				
NLDevices ALDEVICE USF 0 Convect Decice	ed			
Al Devoer Al Devoer END DEVOE VIJE 0 Convect Decome				
Al Devoes EHD DEVICE USF 3 Convect Decome Convect Decome Convect Decome				
At Devices At Devices Convect Oncome Convect Oncome Convect U25	d			
Convers Orecono Convers Orecono Convers Orecono Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Convers Conver	d Hos Care			
Convex Descent 600 000 000 000 000 000 000 000 000 000 000 000 000 000	d His Car			
Al Dences Dences EHD DEVICE UR 0 Convect Dences Convect Dences Dences	PER Class 90 E1 FF 00 81 70			
Al Devices EHD DEVICE U/2-0 Connect Conne	el Plán Caar Statistica Caar Statisti			
All Devices FHD DEVICE V2F 0 Convect Oncome cont 01 OTP - VL3F 01 OTP - COD 024 - COD OV2F - COD 024 - COD	Plane Cane command T do E1 FF 00 01 70 Command T Apply op 1/0 and ond deven successful command T			
Correct Decom EHD DEVICE V2F3 Decom Correct Decom	ed Bloc Clear Contract D ELFF 0001 70 Areby dp Juli and cott device successful Mode workh frain prace put or chogo and agen	·		

After the CCID mode is enabled, the smart card function must be initialized using other Feitian software (GIDS Initialization Tool). This tool can also be downloaded from the Feitian website.

Start the tool in windows, set the desired PIN and Admin key and click Initialize. Please take care in selecting and storing the PIN and Admin key.

	ard Initialization Tool	
The initializat card, if you applet and r	tion operation could perform once only for one want to initialize again, please delete the GIDS e-install it.	
The PIN cou 16 character	ld be number and letter, the length must be 4 to s.	
PIN:	0000	
The Admin K	ey is used to unlock the card if the PIN is locked,	
it is also use hexadecimal	d to reset the PIN. And it must be a 48 characters string.	
it is also use hexadecimal Admin Key:	d to reset the PIN. And it must be a 48 characters string.	
it is also use hexadecimal Admin Key: Initial	d to reset the PIN. And it must be a 48 characters string. 00000000000000000000000000000000000	
it is also use hexadecimal Admin Key: Initial	d to reset the PIN. And it must be a 48 characters string. 000000000000000000000000000000000000	

2. Generating SSH Keys

Once the key is initialized, we can generate SSH keypair and extract the public key. For this, we need to connect it to a computer with OpenSC (version 0.18 or later).

First, we verify that the key is connected and recognized correctly:

[john@Mac-mini ~]\$ opensc-tool --list-readers # Detected readers (pcsc) Nr. Card Features Name 0 Yes FT U2F CCID KB

Next we can dump the contents of the key:

[john@Mac-mini ~]\$ pkcs15-tool -D Using reader with a card: FT U2F CCID KB PKCS#15 Card [GIDS card]: Version : 2 Serial number : dd2de1de707dbd44ba70a1cdc89296 Manufacturer ID: www.mysmartlogon.com Flags : PIN [UserPIN]

Object Flags: [0x3], private, modifiableID: 80Flags: [0x12], local, initializedLength: min_len:4, max_len:15, stored_len:0Pad char: 0x00Reference: 128 (0x80)Type: ascii-numericTries left: 3

Please note the ID number of the PIN, as this is used in the next command as –auth-id parameter, when we generate the publicprivate keypair:

[john@Mac-mini ~]\$ pkcs15-init --verify-pin --auth-id 80 --generate-key rsa/2048 --key-usage sign,decrypt --label "RSA"

Once the key pair is generated, we can list the contents of the device and extract the public key.

[john@Mac-mini ~]\$ pkcs15-tool --list-key Using reader with a card: FT U2F CCID KB Private RSA Key [RSA] Object Flags : [0x1], private : [0x6], decrypt, sign Usage Access Flags : [0x1D], sensitive, alwaysSensitive, neverExtract, local ModLength : 2048 Key ref : 129 (0x81) Native : yes Auth ID : 80 ID : 00 MD:guid : 8d41c334-4ef0-805d-464c-5e8881e5e754 [john@Mac-mini ~]\$ pkcs15-tool --read-public-key 00 Using reader with a card: FT U2F CCID KB -----BEGIN PUBLIC KEY-----MIIBIjANBgkqhkiG9w0BAQEFAAOCAQ8AMIIBCgKCAQEAjFiuFwpwKytBH+igZ9MM nFbcN+M2Cdz4+jpUNuGpDqaKt+bdGyIdqtdkoEws9+G53IBvjHTjWJ9qy09/ck7a a+wwoBbHwDfN8MQ9fyZYkIgIWDY3nNOytsSTCzf8xWp67J2rtCiM4cMbcYXYtYDL CNqACDHvSFk4jir/JpI9Ai8dYX2Y9L9aN8eZlwKVTwbWahkIYsWpa6jrFwxUe9NW nLhdKsG3YLJd6H2Jwe2PWUXul3WHL3NFfkmijTg2tcbyHSX+l4KxFoFOEfzTrVWu zLNQRi4z8O/WzXv46Ra2DXOg3WOOLPM35DGNDE3VK1Wy9WHhlxIPaX5IPQSBIJTM nQIDAQAB -----END PUBLIC KEY-----

With this information we can create an inventory file in .csv format with the right public key. The serial number can be decided by you, as it is only used for keeping track of the devices in WebADM inventory. You can for example user the number printed on the physical device:

"Type","Reference","Description","DN","Data","Status" "PIV Pubkey","1234","FT ePass","","PublicKey=MIIBIjANBgkqhkiG9w0BAQEFAAOCAQ8AMIIBCgKCAQEAjFiuFwpwKytBH+igZ9MMnFbcN-

Next, we can import this file into the WebADM inventory, assign it to a user and test authentication with ssh. These steps are described in Smart Card PIV starting at "We import the file. Under the import tab, we click on Import Inventory File:"

3. Using with a Contactless Reader

The Feitian ePass key supports NFC communication. Thus, it is possible to use the GIDS smart card for authentication also with a contactless reader, resulting a very easy workflow:

[root@fedora28 ~]# pkcs15-tool --read-public-key 00 Using reader with a card: Broadcom Corp 5880 [Contactless SmartCard] (0123456789ABCD) 01 00 -----BEGIN PUBLIC KEY-----MIIBIJANBgkqhkiG9w0BAQEFAAOCAQ8AMIIBCgKCAQEAJFiuFwpwKytBH+igZ9MM nFbcN+M2Cdz4+jpUNuGpDqaKt+bdGyldqtdkoEws9+G53IBvjHTjWJ9gy09/ck7a a+wwoBbHwDfN8MQ9fyZYkIgIWDY3nNOytsSTCzf8xWp67J2rtCiM4cMbcYXYtYDL CNqACDHvSFk4jir/JpI9Ai8dYX2Y9L9aN8eZlwKVTwbWahkIYsWpa6jrFwxUe9NW nLhdKsG3YLJd6H2Jwe2PWUXuI3WHL3NFfkmijTg2tcbyHSX+I4KxFoFOEfzTrVWu zLNQRi4z8O/WzXv46Ra2DXOg3WOOLPM35DGNDE3VK1Wy9WHhlxIPaX5IPQSBIJTM nQIDAQAB

-----END PUBLIC KEY-----

Or in SSH authorized key format, which can also be directly copied to the authorized_keys file in the destination server:

[john@Mac-mini ~]\$ pkcs15-tool --read-ssh-key 00 # Using reader with a card: Broadcom Corp 5880 [Contactless SmartCard] (0123456789ABCD) 01 00 ssh-rsa AAAAB3NzaC1yc2EAAAADAQABAAABAQCMWK4XCnArK0Ef6KBn0wycVtw34zYJ3Pj6OlQ24akOpoq35t0blh2q12 RSA

[john@Mac-mini ~]\$ ssh -I opensc-pkcs11.so user@123.123.35.12 Enter PIN for 'UserPIN (GIDS card)': Last login: Thu Sep 20 15:49:46 2018 from 123.188.35.12 user@host:~\$

If you want to use the smart card authentication without providing the -I flag in the command line, you can configure OpenSC library in ~/.ssh/config (or to /etc/ssh/ssh_config for all users). The correct path the library depends on your system.

PKCS11Provider /usr/lib/opensc-pkcs11.so

This manual was prepared with great care. However, RCDevs Security S.A. and the author cannot assume any legal or other liability for possible errors and their consequences. No responsibility is taken for the details contained in this manual. Subject to alternation without notice. RCDevs Security S.A. does not enter into any responsibility in this respect. The hardware and software described in this manual is provided on the basis of a license agreement. This manual is protected by copyright law. RCDevs Security S.A. reserves all rights, especially for translation into foreign languages. No part of this manual may be reproduced in any way (photocopies, microfilm or other methods) or transformed into machine-readable language without the prior written permission of RCDevs Security S.A. The latter especially applies for data processing systems. RCDevs Security S.A. also reserves all communication rights (lectures, radio and television). The hardware and software names mentioned in this manual are most often the registered trademarks of the respective manufacturers and as such are subject to the statutory regulations. Product and brand names are the property of RCDevs Security. © 2024 RCDevs Security S.A., All Rights Reserved